

DYMO Label Software (DLS) Version 7.8

Platform

- Microsoft Windows 2000
- Microsoft Window XP
- Microsoft Vista

System Requirements

- 20 MB of hard disk space
- 8 MB of available RAM
- CD ROM or Internet connectivity
- Available USB port

Summary of Changes (From Version 7.7 to Version 7.8)

- Added DYMO Stamps button and menu item
- ACT! 2008 Add-in

Summary of Changes (From Version 7.6 to Version 7.7)

- Support for 32-bit and 64-bit editions of Windows Vista
- Support for Microsoft Office 2007
- ACT! 2007 Add-in
- Serial connected LabelWriter printers are no longer supported

Summary of Changes (From Version 7.5 to Version 7.6)

- Support for Continuous Wide labels
- New Add-in for Microsoft Excel
- Improved Microsoft Word Add-in
- Improved performance for Microsoft Outlook Add-in
- Updated WordPerfect Add-in to support WordPerfect 13
- Updated documentation
- Windows 98 and Windows ME are no longer supported
- The Add-ins included with DLS 7.6 no longer support Microsoft Office 97

Summary of Changes (From Version 7.2 to Version 7.5)

- Support for the new ExecuLabel LM450 (LabelManager 450), ExecuLabel LP350 (LabelPoint 350), and LabelManager PC II tape printers
- Updated drivers featuring improved image print quality
- Improved tape editor layout and font handling
- ACT! 2006 Add-in
- Text object automatically added when creating a new label template

Summary of Changes (From Version 7.1 to Version 7.2)

- Support for the LabelWriter Twin Turbo printer
- Support for ACT! 2005 Premium

Summary of Changes (From Previous Versions to Version 7)

- Support for the new LabelWriter 400, 400 Turbo, and Duo printers
- Updated drivers for the LabelWriter 300 series printers
- ACT! 2005 Add-in
- WordPerfect 12 Add-in

Printer Compatibility

DLS Supports the following printer models

Windows 2000 and Windows XP	Windows Vista
LabelWriter 400	LabelWriter 400
LabelWriter 400 Turbo	LabelWriter 400 Turbo
LabelWriter Duo	LabelWriter Duo
LabelWriter Twin Turbo	LabelWriter Twin Turbo
LabelWriter 300	LabelWriter 310 (models 90966, 93029 & 93034 ONLY)
LabelWriter 310	LabelWriter 315 (model 90975 ONLY)
LabelWriter 315	LabelWriter 320 (models 90892, 93031 & 93036 ONLY)
LabelWriter 320	LabelWriter 330 (model 90891 & 93037 USB ONLY)
LabelWriter 330	LabelWriter 330 Turbo (models 90884, 93033 & 93038, USB ONLY)
LabelWriter 330 Turbo	LabelManager PC II
LabelManager PC & LabelManager PC II	LabelManager 450
LabelManager 450	LabelPoint 350
LabelPoint 350	

Installation

Administrator Rights

You must install DLS from a user account with Administrator rights. However, you can use the software while logged in to an account with Limited rights.

Upgrading from Windows XP to Windows Vista

When upgrading from Windows XP to Windows Vista, the Windows XP DYMO Label printer drivers will not work correctly. You **must** install this version of DYMO Label Software to install label printer drivers with Vista support.

New LabelWriter Printer Installations in Windows Vista

If you connect the printer before running the installer, the Windows XP version of the printer driver may be installed. If this happens, you must delete this printer driver and then run the installer.

Connecting to Shared Printers with Windows Vista

If you want to connect to a shared network printer, use the Windows Vista Add Printer Wizard in the Printer control panel to connect to the shared printer.

Upgrading from a Previous Installation of DLS

- If you are upgrading from DLS version 6, all label files and address book files should continue to work with DLS 7. All existing Label Template files, Address Book files, and Clip Art files will be copied and saved into:
C:\Documents and Settings\All Users\Documents\DYMO Label
- It is recommended that you back up the following folders before upgrading to DLS 7:
C:\Program Files\DYMO Label\Address Books
C:\Program Files\DYMO Label\Label Files
- Do not uninstall your previous installation of DLS. Simply running the DLS 7 installer will update all necessary files.

Installing a LabelWriter 400 Series Printer on a Workstation with a Previous LabelWriter Installation

Workstations that previously had or currently have a LabelWriter XL, EL, or 300 series printer installed may require that you uninstall these printer drivers prior to installing a LabelWriter 400 series printer. You will have to uninstall any previously installed LabelWriter printer drivers if:

- An EL or XL series printer has been previously installed or is currently installed.
- A serial connected LabelWriter has been previously installed or is currently installed.
- A networked LabelWriter has been previously installed or is currently installed.

Uninstalling Previously-Installed LabelWriter Printer Drivers

Note: Uninstalling DLS will **not** uninstall LabelWriter printer drivers.

1. In the **Printers** folder, do the following:
 - Delete any print jobs that may be present for any LabelWriter printer.
 - Delete any networked Costar/DYMO printers.
2. When DLS was initially installed, a sub folder entitled **Support Files** was created in the **DYMO Label** folder. In this folder is a file, **LWRemove.exe**, with a trash can icon. Turn off the LabelWriter and run **LWRemove.exe**.
 - Regardless of what appears in the **DYMO Printer Driver Uninstaller** dialogue window, click on **Select All** and then **Remove**.
 - Restart your computer once the driver uninstallation is complete.
3. After rebooting, install DLS 7 and follow the on-screen instructions.
 - When prompted to plug in your USB LabelWriter printer(s), connect the LabelWriter 400 series printer first.
4. Once the DLS installer has completed, connect any other USB LabelWriter printer(s) and the new drivers will install automatically.
 - **Note:** Serial-connected LabelWriter printers and networked LabelWriter printers need to be installed manually from the **Add Printer Wizard** located in the **Printers** folder.

Special Instructions and Important Notes

- This software does not support Windows 95, 98, ME, or NT. For Windows 95 and NT, install DLS version 4.2.1. For Windows 98 and ME, install DLS version 7.5.
- DLS 7 does not include drivers for XL and EL series printers. For XL and EL series printers, install DLS version 6.1.
- Using serial to USB adapters is not supported.

Contacting DYMO Technical Support

For Technical Support, please visit the Support section of the DYMO Web site at: <http://www.dymo.com>